

Release Notes

System Software 2.4.3.5

1	Release 2.4.3.5.....	2
1.1	Note	2
2	Changes.....	2
3	Error corrections.....	2

1 Release 2.4.3.5

1.1 Note

This version is only available for the W2022ac/W2022ac-ext devices. To install release 2.4.3.5, it is necessary that release 2.4.1.1 or higher is already installed on the access point. To install release 2.4.3.5 from an even older version, you must first install version 2.4.1.1.

2 Changes

- Release 2.4.3.5 supports a newly introduced **flash module** in production. Changes in the scope of functions do not result from this change. Devices manufactured from February 2022 (you will find the date on the type plate of your device) are equipped with this module and therefore prevent a downgrade to an earlier version of the system software.

3 Error corrections

- In rare cases, when updating the system software via the graphical user interface of the access point, the error message *ERROR: fd read problems (data length mismatch)* was displayed when using the *Local file* option as the source of the software image. This error does not occur when using the *Current software from update server* or *External server* source, so these two methods should be preferred. If the error occurs, **do not restart the access point**, but click **Back** in the pop-up window and perform the update again using one of the two preferred recommended methods. With release 2.4.3.5 this error has been fixed, so that from this version onwards an update can be performed from a local source again.

4 Known issues

- **(ER#5567)** - The local IP address of the access point is not communicated to the Cloud Net Manager in the system status information.
- **(ER#5646)** - The local GUI is locked as soon as the access point is managed via the **Cloud Net Manager**. As a workaround, a reset to the ex works state can be performed on the access point by pressing the reset button during the startup phase.