


Important information about System Software Release 3.2.1.1:

- **This release cannot be used for productive operation.**
- **It cannot be used on W2044ax access points.**

If your access point is delivered with system software version **3.2.1.1**, do not operate it with this software, as this version is only intended for the manufacturing process. Instead, update your device to system software version **3.2.1.2** or higher before putting it into operation.

Moreover, system software version 3.2.1.1 is not released for the use with **W2044ax** access points.

You can find the update option in the menu **Maintenance > Software & Configuration**:



Software and Configuration Options

Action	Update system software ▾
Allow Software Downgrade	<input type="checkbox"/> Disabled
Source Location	Local File ▾
Filename	<input type="text"/>

- Local File
- External Server
- Current Software from Update Server

If your access point does not yet have internet access, you can also download the software image from our server (<https://archive.bintec-elmeg.com/?dir=Files/WLAN/IMG-Series>) and then carry out the update by choosing the option *Local File* for the **Source Location**.


Wichtige Information zu Systemsoftware Release 3.2.1.1:

- **Dieses Release kann nicht für den produktiven Einsatz verwendet werden.**
- **Es kann nicht auf W2044ax-Access-Points verwendet werden.**

Wenn Ihr Access Point mit der Systemsoftware-Version **3.2.1.1** ausgeliefert wird, nehmen Sie ihn nicht mit dieser Software in Betrieb, da diese Version nur für den Herstellungsprozess vorgesehen ist. Aktualisieren Sie stattdessen Ihr Gerät auf die Systemsoftware-Version **3.2.1.2** oder höher, bevor Sie es in Betrieb nehmen.

Außerdem ist die Systemsoftware Version 3.2.1.1 nicht für die Verwendung mit **W2044ax** Access Points freigegeben.

Die Update-Option finden Sie im Menü **Wartung > Software & Konfiguration**:



Wenn Ihr Access Point noch keinen Internetzugang hat, können Sie das Software-Image auch von unseren Sever herunterladen (<https://archive.bintec-elmeg.com/?dir=Files/WLAN/IMG-Series>) und dann das Update durchführen, indem Sie die Option *Lokale Datei* für den **Quellspeicherort** wählen.